

Remote Desktop Connection and Remote Settings

For security purposes, you **CANNOT** remote into your work computer unless you're connected via **FIRST** from a **VPN Client** on your off-campus computer. Also, your office computer does not accept a remote desktop connection by default. If a remote desktop connection to your office computer is desirable, please read the following:

 On your desktop, right-click This PC shortcut and select Properties. Note: If there is no shortcut on the desktop, open File Explorer and right-click This PC in the left pane.



Open
Pin to Quick access
Manage
Pin to Start
Map network drive
Disconnect network drive
Create shortcut
Delete
Rename
Properties



2. This will open the **System** menu then select **Remote Settings** on the left panel.

¥	System						_		×
÷	$ ightarrow ~ \uparrow 👱 > ightarrow Control Pane$	> System and Security > System ~	ē	Q	S	earch C	ontrol	Panel	
•	Control Panel Home	View basic information about your compute	er						?
	Device Manager	Windows edition							
~	<u>Remote settings</u>	© 2019 Microsoft Corporation. All	۱ ۸	Windows10					
V	System protection		V۱						
•	Advanced system settings	rights reserved.							\sim
		Suctem							



- 3. Under **Remote Assistance.** Check **Allow Remote Assistance** connections to this computer.
- 4. Under **Remote Desktop.** Enable Allow remote connections to this computer.
- 5. Under **Remote Desktop.** Check Allow connections only computers running **Remote Desktop** with **Network Level Authentication**.
- 6. Click Apply then OK.

System Properties			×				
Computer Name H	ardware Advanced	System Protection	Remote				
Remote Assistance	Remote Assistance						
Allow Remote	Assistance connectio	ns to this computer					
What happens w	nen I enable Remote /	Assistance?					
		Ad	lvanced				
Remote Desktop							
Choose an option	, and then specify wh	o can connect.					
O Don't allow ren	O Don't allow remote connections to this computer						
Allow remote c	Allow remote connections to this computer						
Allow connections only from computers running Remote Desktop with Network Level Authentication (recommended)							
Help me choose		Sele	ect Users				
	ОК	Cancel	Apply				



Once your office computer is set up to accept authorized remote desktop connection:

From a remote Windows 10 computer,

7. On the **Start Menu** type in **Remote Desktop Connection** & select **Remote Desktop Connection** on the top.





8. Type in yourcomputername.vsoe.usc.edu then click on Connect.

퉣 Remote			\times		
N	Remote Desktop Connection				
Computer: User name:	yourcomputername.vsoe.usc.edu None specified	4	~		
You will be as	sked for credentials when you conn ptions	ect. Connect		Help	

- 9. To find your computer name, right click on **This PC** & select **Properties.**
- 10. Under Computer name, domain, and workgroup settings look for Full Computer Name.
- 11. You will be prompted to enter your credentials for your computer. Login as you would at work. Enter: vsoe\username and password.
- 12. Click **OK**.

Windows Security	×					
Enter your credentials						
These credentials will be used to connect to hb.vsoe.usc.edu.						
vsoe\yourusername]					
•••••						
Remember me						

13. Once connected, you are able to access your resources on your remote computer.



Remote Desktop Mac

1. Go to the App Store and search for Microsoft Remote Desktop.



- 2. Click Get to download the app. You will need to enter you Apple ID credentials.
- Once done, launch the app and click '+' icon and select Add PC at the top of the Microsoft Remote Desktop window.







School of Engineering

4. Enter your PC name or IP address.





5. For User Account, select Add User Account, enter your credentials for your computer. Enter: vsoe\username and password then click Add.

Add User Account						
Username:	Domain\user or user@domain					
Password:	Optional					
Friendly name:	Optional					
	Cancel Add					





6. To start the connection, double-click on your PC Name thumbnail.





7. Click **Continue**.

$\textcircled{\begin{tabular}{c} \bullet \bullet \bullet \\ \bullet \bullet \bullet \end{array}$			
	You are connecting to the RDP hos be verified back to a root certificat you want to continue?	t "102.100.1.05". The certifi te. Your connection may not	cate couldn't be secure. Do
	Show Certificate	Cancel	Continue